

Spectra Firmware Update 20190917

Dear customers,

We have released the new firmware for the following system optimization.

1. Fix the incompatible issue with some Android Apps
2. Power management optimization for iOS system

A . Firmware download link

Windows : https://download.nextdrive.io/spectra/spectra_windows.zip


MAC : https://download.nextdrive.io/spectra/spectra_macos.zip

B .Steps for installation

● Windows

Step:

1. Plug Spectra into your computer and make sure Spectra's indicator light keep in blue.
2. Unzip the setup file and execute the "setup.exe" and you will see the notification as below. Please choose " Y "



3. Press " **Write EEPROM** " and the setup program will update firmware of Spectra automatically, and don't click the box above. (Please be noted: don't remove Spectra at this moment or it possibly causes Spectra damage.




4. The following notification pops up which means all the process is complete.



5. Press "OK". Remove Spectra from computer. It is done!


● MAC

1. Plug Spectra into your computer and make sure Spectra's indicator light keep in blue.
2. Unzip the file "[spectra_macos](#)" and then execute the setup file.
3. First, you might see the notice as below.




4. Go to 【System Preferences】 → 【Security&Privacy】


Then, you will see the following setting page. Please choose "Open Anyway" to enable the setup file.




5. It will pop up a notification which need your confirmation. Please choose “ **Open** ”



6. Go back to setup file and execute it again. You will see the following notification. Please choose “ **Y** ”



7. Press “ **Write EEPROM** ” and the setup program will update firmware of Spectra automatically. (Please be noted: don’t remove Spectra at this moment or it possibly causes Spectra damage.)



8. When you see the following page, it means the firmware update is done.

